

Clonogenic Assay to Test Cancer Therapies

Xiaodong Yang*

Department of Neurology, University of California, San Francisco, USA

*For correspondence: yangxiaodong1@yahoo.com

[Abstract] Clonogenic assays serve as a useful tool to test whether a given cancer therapy can reduce the clonogenic survival of tumor cells. A colony is defined as a cluster of at least 50 cells that can often only be determined microscopically. A clonogenic assay is the method of choice to determine cell reproductive death after treatment with ionizing radiation, but can also be used to determine the effectiveness of other cytotoxic agents. The following protocol has been modified from a published version (Franken *et al.*, 2006).

Materials and Reagents

1. Cell culture medium
2. Phosphate buffered saline (PBS)
3. Fetal bovine serum (FBS)
4. Trypsin/ EDTA (Life Technologies, Invitrogen™, catalog number: 25200-056)
5. Crystal violet (Sigma-Aldrich, catalog number: C3886)
6. Methanol (Sigma-Aldrich, catalog number: 34860)
7. Glacial acetic acid (Sigma-Aldrich, catalog number: 320099)
8. Fixation solution
9. Colony fixation solution (see Recipes)
10. Crystal violet solution (see Recipes)

Equipment

1. Cell culture petri dishes or six-well plates (Thermo Fisher Scientific, catalog number: 08-772-1B)
2. Hemocytometer (Hausser Bright-Line) (Thermo Fisher Scientific, catalog number: 02-671-10)
3. Stereomicroscope (*e.g.*, Nikon Eclipse, model: TS100)
4. Hemocytometer
5. Incubator

Procedure

A. Cell preparation:

1. Culture the cells according to the requirement (e.g., GBM cell lines, U87, U251, SF188, etc).
2. Remove medium, and then rinse cells with 10 ml PBS.
3. Add 4 ml 0.25% trypsin to the cells and incubate at 37 °C for 1-5 min until the cells appear round.
4. Add 10 ml medium with 10% FBS, and detach the cells by pipetting.
5. Count the cells using a hemocytometer.
Note: It is critical to get a relatively accurate number for the cells.
6. Prepare desired seeding concentration, and then seed cell into dishes or 6-well plates.

B. Assay setup:

Cell can be plated either before or after the treatment.

1. Plating before treatment:
 - a. Harvest cells and plate an appropriate number of cells per dish or per well on a 6-well plate, at least in duplicate. The number of cells for seeding should be determined by the aggressiveness of the treatment. Incubate cells for a few hours in a CO₂ incubator at 37 °C and allow them to attach to the plate/dish.
 - b. Treat the cells as necessary with chemicals (e.g., 1-100 μM), radiation (e.g., 2-10 Gy) or a combination of both.
 - c. Incubate the cells in a CO₂ incubator at 37 °C for 1-3 weeks until cells in control plates have formed colonies that are of a substantially good size (50 cells per colony is the minimum for scoring).
2. Plating after treatment:
 - a. Harvest cells after treatment. Fifty or up to 50 x 10⁴ cells can be plated. Prepare serial dilutions with different numbers of cells, should the effects of the treatments be unclear. For radiation treatment, the cells can be plated immediately after treatment or re-plated later. It is always better to keep the cells on ice before re-plating.
 - b. Incubate the cells in a CO₂ incubator at 37 °C for 1-3 weeks until cells in control plates have formed colonies with substantially good size (50 cells per colony is the minimum for scoring).

C. Fixation and staining:

1. Remove medium, and then rinse cells with 10 ml PBS.

2. Remove PBS and add 2-3 ml of fixation solution and leave the dishes/plates at room temperature (RT) for 5 min.
3. Remove fixation solution.
4. Add 0.5% crystal violet solution and incubate at RT for 2 h.
5. Add 10 ml medium with 10% FBS, and detach the cells by pipetting.
6. Remove crystal violet carefully and immerse the dishes/plates in tap water to rinse off crystal violet.
7. Air-dry the dishes/plates on a table cloth at RT for up to a few days.

D. Data analysis:

1. Count number of colonies with a stereomicroscope.
2. Calculate plating efficiency (PE) and surviving fraction (SF).

$$PE = \text{no. of colonies formed} / \text{no. of cells seeded} \times 100\%$$

$$SF = \text{no. of colonies formed after treatment} / \text{no. of cells seeded} \times PE$$

Recipes

1. Colony fixation solution
 Acetic acid/methanol 1:7 (vol/vol)
2. Crystal violet 0.5% solution

Acknowledgments

This protocol has been modified from a published version (Franken *et al.*, 2006).

References

1. Franken, N. A., Rodermond, H. M., Stap, J., Haveman, J. and van Bree, C. (2006). [Clonogenic assay of cells *in vitro*](#). *Nat Protoc* 1(5): 2315-2319.
2. Mueller, S., Yang, X., Sottero, T. L., Gragg, A., Prasad, G., Polley, M. Y., Weiss, W. A., Matthay, K. K., Davidoff, A. M., DuBois, S. G. and Haas-Kogan, D. A. (2011). [Cooperation of the HDAC inhibitor vorinostat and radiation in metastatic neuroblastoma: efficacy and underlying mechanisms](#). *Cancer Lett* 306(2): 223-229.
3. Prasad, G., Sottero, T., Yang, X., Mueller, S., James, C. D., Weiss, W. A., Polley, M. Y., Ozawa, T., Berger, M. S., Aftab, D. T., Prados, M. D. and Haas-Kogan, D. A. (2011). [Inhibition of PI3K/mTOR pathways in glioblastoma and implications for combination therapy with temozolomide](#). *Neuro Oncol* 13(4): 384-392.